Blouse With Lace Inserts - Выкройка #2888



Recommendations on fabric: natural/mixed fabrics suitable for blouses. Lace fabric.

You will also need: fusible interfacing.

Seam allowances: Seam allowance for hem of garment – 2 cm; other seams – 1 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Back - cut 1 on fold
2. Front – cut 2
3. Stand collar – cut 2
4. Upper sleeve – cut 2
5. Lower sleeve – cut 2

Lace fabric:

1. Front decoration – cut 2
2. Front edge trim – cut 2
3. Sleeve inset – cut 2

Fusible interfacing:
1. Stand collar – cut 1

Инструкции:

1. Apply fusible interfacing to the stand collar.

2. Sew the darts on the front pieces, trim the dart depths to 1 cm, and press away from the center, serge.

3. Press the long edges of the front trim to the wrong side, place the trim on the front according to the markings, and topstitch.

4. Place the front edge trim and the front wrong sides together and sew the front edge. Press the seam allowances open, then lay the front and trim flat in one plane. Place the fronts right sides together, matching the edge-finishing seams, and sew in this seam from the mark to the lower edge. Turn the pieces out, press the long edges of the front edge trim to the wrong side, and topstitch it onto the front.

5. Sew shoulder and side seams, press towards the back and serge.

6. Pin stand collars together right sides together and sew outer edges. Start and stop sewing exactly at the marked line of seam. Clip into curves, turn stand collar right side out, straighten and press.

7. Sew outer stand collar into neckline, press seam allowances at stand collar. Turn under the unfinished edge of inner stand collar and stitch in the ditch.

8. Sew the sleeve insert to the upper sleeve part, press seam allowances towards sleeve, serge. Sew the lower sleeve part to the insert, press seam allowances towards sleeve, serge.

9. Serge the sleeve edges separately. Sew the sleeve seam from the armhole to the end of the lace insert. Press the seam allowances open, pressing the slit flat. Stitch along the edge of the slit 0.1 cm from the fold.

10. Sew a gathering stitch along the sleeve cap and gather fullness. Sew sleeves into armholes, serge and press.

11. Sew a gathering stitch along lower edge of sleeve and gather fullness. Sew bias tape to lower edge of sleeve (pin bias tape to edge from the right side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line), sewing the ties at the same time.

12. Serge the lower edge of garment, press onto wrong side and topstitch.

Технический рисунок:

