

Dress With A Deep Neckline - Выкройка #2921

Recommendations on fabric: thick natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; dress zipper.

Seam allowances: all seams 1 cm; seam allowance for hem of garment – 2.5 cm.

О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Upper back - cut 2
2. Lower back - cut 2
3. Upper front - cut 2
4. Lower front - cut 1 on fold
5. Slit facing – cut 2
6. Stand collar – cut 2

7. Belt – cut 1 on fold

Fusible interfacing:

1. Slit facing – cut 2
2. Stand collar – cut 1
3. Belt – cut 1 on fold

Инструкции:

1. Apply fusible interfacing.
2. Sew darts on upper back, press bulk towards center. Sew upper back to lower back, press towards top and serge.
3. Serge center back edges separately on each piece. Sew the center seam from the neckline to the zipper mark and from the lower zipper mark to the bottom edge, press the seam apart. Sew in zipper.
4. Sew darts on upper fronts. Trim bulk with serger and press towards center.
5. Serge outer edge of slit facing. Place the neckline slit facing on the right side of the front and sew the neckline slit. Fold the facing onto wrong side and press. Sew the upper fronts together from the mark to the bottom edge, folding the slit facings out of the way.
6. Sew upper front to lower front, press towards top and serge.
7. Sew shoulder seams, press towards the back and serge.
8. Pin together parts of stand collar, right sides together and sew upper edge, start and stop stitching exactly at the marked sewing line. Clip into curves, trim away corners, turn stand collar right side out and press. Place the outer stand collar and the garment right sides together and sew it to the front and back, matching the marks. Press the seam allowances toward the stand collar. Fold the raw edges of the inner stand collar to the wrong side and stitch in the seam joining the outer stand collar.
9. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of armhole + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape onto armhole edge from the right side and sew. Fold bias tape onto wrong side and topstitch onto main piece along the fold. Press seam.
10. Sew side seams, press towards the back and serge.
11. Serge bottom edge of garment, press onto wrong side and topstitch.
12. Fold belt in half lengthwise right sides together and sew, leaving an opening for turning. Trim away corners,

turn right side out. Sew the opening closed and press.

Технический рисунок:

