Dress With Asymmetric Buttons - Выкройка #2935



Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 5 buttons; dress zipper; shoulder pads; lining.

Seam allowances: Seam allowance for hem of garment – 2 cm; other seams – 1 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Center back - cut 2
2. Side back - cut 2
3. Center front - cut 2
4. Side front - cut 2
5. Back neck facing – cut 2
6. Front neck facing - cut 2

Lining:
1. Back lining – cut 2
2. Center front lining – cut 2
3. Side front lining – cut 2

Fusible interfacing:
1. Back neck facing – cut 2
2. Front neck facing - cut 2

Инструкции:

1. Apply fusible interfacing.

2. Stitch the shoulder seams of the center dress pieces. Clip seam allowances and press apart.

3. Stitch the princess seam of the front lining pieces and press the seam allowances. Sew the front lining to the front neckline facing. Press the seam allowance toward the lining.

4. Stitch the dart on the back lining and press the dart intake toward the center. Sew the back lining to the back neckline facing. Press the seam allowance toward the lining. Sew side and shoulder seams of lining and of facings. Clip the seam allowances along the curves and press them open. Serge lower edge of lining.

5. Place the facings on the front and back, right sides together, and stitch the neckline. Clip seam allowances, turn right side out and press.

6. Put right front onto left front and baste together along princess seams.

7. Stitch the shoulder seams of the side dress pieces. Press the seam apart.

8. Stitch the princess seams of the front and back in one continuous seam, serge seams and press towards center.

9. Sew side seams. Press seams towards back and serge.

10. Sew lining to armhole in two steps: first sew the front armhole, then sew the back armhole. Clip seam allowances, turn right side out and press.

11. Serge center back edges separately, folding the lining aside. Sew center back seam from notch for zipper to bottom, press the seam apart. Sew in zipper. Sew the back neckline facing and the lining to the zipper tape by hand.

12. Sew on shoulder pads.

13. Turn hem under inside at 1 cm, then again at 1 cm and topstitch.

14. Sew decorative buttons according to markings.

Технический рисунок:

