

## Dress With Guipure Yoke - Sewing Pattern #4405

Recommendations on fabric: natural/mixed fabric suitable for dresses; guipure.

You will also need: lining fabric in a matching color to guipure, dress zipper, fusible interfacing.

Seam allowances: all seam allowances 1 cm; seam allowance for hem of dress - 2.0 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Lower back - cut 2
2. Lower front - cut 1
3. Center front - cut 2
4. Stand collar - cut 1

Guipure:

1. Upper back - cut 2

2. Upper front - cut 1

Lining:

1. Upper back - cut 2
2. Upper front - cut 1
3. Center front - cut 2
4. Stand collar - cut 1

Fusible interfacing:

1. Stand collar - cut 1

## **INSTRUCTIONS:**

1. Apply fusible interfacing to stand collar from lining.
2. Sew darts on upper backs and lower backs, cut away the bulk of the dart leaving 1 cm. Serge seams and press towards center. Sew darts on upper fronts. Press bulk towards center. Repeat for lining.
3. Guipure: Sew shoulder seams, press the seam apart. Подкладочная fabric: Sew shoulder seams, press the seam apart. Serge lower edges of lining. Sew guipure stand collar into neckline. Sew stand collar of lining into neckline of bodice of lining.
4. Sew upper back to lower back, serge seams and press towards top.
5. Serge center back edges separately. Sew center back seam from zipper marker down to slit corner. Press the seam apart, pressing the slit at the same time. Sew in zipper. Topstitch sides of slit at 0.1 cm from fold.
6. Make and baste pleats on lower fronts. Sew upper front to lower front, serge seams and press towards top.
7. Make and baste pleats on center front, put together with lining and sew upper and lower edges. Turn right side out, straighten and press. Put center fronts on front and baste along side seams.
8. Put together lining and dress right sides together and sew edge of stand collar. Sew armholes in two steps: first sew front armhole and then sew back armhole. Clip into curves. Turn right side out, press. Baste together seam allowances where stand collars have been sewn into garment.
9. Sew side seam on lining and main fabric with one continuous seam. Serge seams and press towards back. Slipstitch lining to zipper tape and seam between lower and upper parts of dress.
10. Serge bottom edge of dress, press onto wrong side and finish with hidden stitches.

**TECHNICAL DRAWING:**

