

## Dress In Vintage Style - Sewing Pattern #4427

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; dress zipper, 5 buttons.

Seam allowances: all seams 1 cm; seam allowance for hem of dress and hem of sleeve – 2 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Center back - cut 2
2. Side back - cut 2
3. Center front - cut 1
4. Side front - cut 2
5. Front yoke - cut 2
6. Back yoke - cut 4

7. Sleeve – cut 2

## **INSTRUCTIONS:**

1. Sew side backs to center back. Sew side fronts to center front. Serge the seam allowances and press towards center.
2. Serge center back edges separately. Sew center back seam from notch for zipper to bottom. Seam Allowances  $\text{шва}$  press apart, pressing the slit at the same time. Sew in zipper. Sew back yoke to yoke. Press seam allowance towards top. Center edge of yoke protrudes by 1 cm!
3. Sew a gathering stitch on upper edge of center front and gather fullness. Sew yoke to front. Press seam allowance towards top.
4. Sew shoulder seams sewing the stand collar seam at the same time. Press the seam allowances apart.
5. Make a rouleau cord for bias fabric buttonhole loops (cut bias tape approximately 2.5 cm wide, fold in half lengthwise and press, sew a few millimeters from the edge and turn right side out). Cut into 5 parts.
6. Sew shoulder seams sewing the stand collar seam on inner yokes at the same time. Press the seam apart. Serge the lower edges of yokes. Pin together outer and inner yokes right sides together and sew neckline. Sew center edge on back, inserting loop buttonholes. Clip into seam allowance. Fold away the inner yokes onto wrong side and press neckline. Baste yokes together along armhole edges (treat as one piece in the future). Topstitch inside yokes into seam of outer yokes.
7. Sew side seams. Serge seams and press towards back.
8. Sew sleeve seam. Serge and press towards back. Sew sleeve into armhole. Serge.
9. Serge lower edge of dress and lower edge of sleeve, press onto wrong side and topstitch. Sew on buttons.

## **TECHNICAL DRAWING:**

