

## Blouse With Lace - Sewing Pattern #4450

Recommendations on fabric: Блузочные ткани из натуральных or смесовых волокон.

You will also need: 6 buttons, decorative tape-lace , its width should equal 5 cm (when ready it will equal 4 cm).

Seam allowances: seam allowance for hem of garment — 1.5 cm, other seams 1 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Back yoke — cut 1
4. Center front – cut 2
5. Side front – cut 2
6. Front yoke — cut 2

- 7. Sleeve-cut 2
- 8. Stand collar — cut 2

Fusible interfacing :

- 1. Placket - cut 2
- 2. Stand collar — cut 1

## **INSTRUCTIONS:**

1. Apply fusible interfacing to stand collar and wholecut placket.
2. Sew side fronts to front, sew side backs to back. Serge seams and press towards center. Sew center back seam. Serge the seam allowances and press towards left. Sew back yoke to garment. Serge and press onto yoke.
3. Serge center edge of front yoke. Sew lace to yoke. Seam Allowances press onto yoke. Sew yoke to front. Serge and press onto yoke. Fold wholecut placket onto wrong side and sew upper straight part. Fold placket onto right side and press. Fold long edge of placket onto wrong side, fold seam allowance inside and topstitch at 0.2 cm from the edge.
4. Sew shoulder and side seams. Serge seams and press towards back.
5. Pin together parts of stand collar right sides together and sew around upper edge and corners. Trim seam allowances, turn right side out and press. Sew upper stand collar into neckline. Turn inside the seam allowance of lower stand collar and stitch-in-the-ditch along seam of upper one stand collars.
6. Serge lower edge of sleeve. Sew decorative tape to sleeve. Press seam allowance towards sleeve. Sew a gathering stitch along upper edge of sleeve cap and gather fullness. Sew sleeve into armhole. Serge seam allowances on armhole. Fold inside seam allowance of lower part of armhole and topstitch.
7. Serge the lower edge of garment. Fold seam allowance onto wrong side, press and topstitch.
8. Make buttonholes on right side, sew on buttons on left side.

## **TECHNICAL DRAWING:**

