

Light Coat With Hidden Button Panel - Sewing Pattern #4478

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: lining; fusible interfacing; 5 buttons; shoulder pads.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve - 3.5 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back - cut 2
2. Front - cut 2
3. Stand collar - cut 2
4. Upper sleeve - cut 2
5. Lower sleeve - cut 2
6. Back neck facing - cut 1
7. Center front facing - cut 2

Lining:

1. Back - cut 2
2. Front - cut 2
3. Upper sleeve - cut 2
4. Lower sleeve - cut 2
5. Lining of hidden button panel - cut 2

Attention: Lining for back and front is cut using pattern blocks for main fabric except for back neckline facing and buttonstands accordingly..

Fusible interfacing:

1. Front - cut 2
2. Center front facing — cut 2
3. Stand collar - cut 1
4. Back neck facing — cut 1
5. Lining of hidden button panel - cut 1

Fusible interfacing is also applied to sew allowances along armhole спинки, lower edge of garment and hem of sleeve.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew darts on back, press bulk towards center. Apply fusible interfacing to vent areas on the back on the wrong side. Mark center seam line (vent fold-line) from the right side. Press left back along fold line of vent. Align pieces along center seam. Sew center back seam and corner of vent, stop stitching when the distance from vertical edge of vent is 1 cm. Clip into seam allowance of vent in corner on right part. Press apart center seam, press seam allowances of vent and topstitch them from the right side using machine stitch.
3. Sew darts on front, clip into curves and press apart.
4. Sew outer stand collar into back neckline, clip seam allowances and press apart.
5. Sew shoulder seams of coat sewing the stand collar seam at the same time, clip seam allowances and press apart. Sew side seams, press seam apart.
6. Mark тремя линиями прорезь застежки at лицевой стороне правого center front facings: первая линия параллельна линии center front facings and проходит at 1.5 cm from edge center front facings into готовом виде; второй and третьей линией ограничить длину застежки. Положить продублированную подкладку onto right side center front facings лицевой стороной down into направлении from edge center front facings, matching край среза of lining and намеченную линию. Sew a stitch at 0,5 cm от намеченной линии along the slit застежки to линий, ограничивающих длину застежки . Приложить вторую подкладку застежки

встык to строчке притачивания первой of lining and sew a stitch at 0,5 cm. Проверить правильность притачивания подкладок from the wrong side (stitch lines should be parallel). Прорезать отверстие. At расстоянии 1,5 cm от конца прорези застежки сделать наклонные разрезы. Through The полученное отверстие of lining turn right side out onto wrong side, образуя из продублированной of lining рамку, равную ширине между строчками. Проложить закрепляющую строчку into seam of of lining. Вторую подкладку press into сторону внутреннего среза center front facings and sew a fixing stitch at 0,1 cm from seam of lining. Mark and make buttonholes . Buttonloops пробиваются at подборте вместе с дублированной подкладкой. Straighten and slipstitch концы застежки с изнанки двойной обратной строчкой by основанию углов. Sew edges подкладок. Поставить закрепки между каждой парой петель, длина закрепки равна ширине рамки. Press center front facing.

7. Sew inner stand collar into neckline facings, clip seam allowances and press apart. Sew shoulder seams of buttonstands and facings, continue sewing the seam of stand collars, press seam apart.

8. Press seam allowance on lower edge. Pin buttonstand onto front right sides together, sew buttonstands and edge of stand collar. Sew corner of buttonstand, stepping back from inner size of buttonstand at 1.5 cm. Trim away corners, turn buttonstands and stand collar right side out onto right side, straighten seams.

9. Sew the elbow seam of the sleeve and press it apart. Press hem of sleeve. Sew and press apart front sleeve seam. Sew sleeve into armhole. Sew on shoulder pads.

10. Sew seams on lining, leaving an opening in left side seam for turning. Sew in sleeves. Sew lining to buttonstands and facing.

11. Sew lining to lower edge of garment, vent and lower edge of sleeve. Turn coat right side out through the opening. Sew the opening closed.

12. Sew a decorative stitch on right front according to markings, fixing in place hidden button panel. Sew on buttons according to button holes.

TECHNICAL DRAWING:

