

## Coat With Decoration On Sleeves - Sewing Pattern #4750

Recommendations on fabric: thin natural/mixed fabric suitable for coats.

You will also need: lining; fusible interfacing; hook and eye, 5 flat buttons for hidden placket, decoration for sleeves.

Seam allowances: all seams 1 cm; seam allowance for hem of garment and hem of sleeve – 3 cm.

### Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

### Note on length of fabric:

*Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.*



## CUTTING:

### Note on cutting:

*On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.*

*When sewing the garment, pay attention to notches, they must match up.*

Main fabric:

1. Back yoke – cut 1
2. Back - cut 2
3. Front yoke – cut 2
4. Front - cut 2
5. Center front facing - cut 2
6. Collar - cut 2

- 7. Back neck facing – cut 1
- 8. Upper sleeve – cut 2
- 9. Lower sleeve – cut 2

Lining:

- 1. Back lining - cut 2
- 2. Front lining - cut 2
- 3. Upper sleeve – cut 2
- 4. Lower sleeve – cut 2
- 5. Lining of hidden button panel – cut 2

Fusible interfacing:

- 1. Collar – cut 1
- 2. Center front facing- cut 2
- 3. Back neck facing – cut 1

## INSTRUCTIONS:

- 1. Apply fusible interfacing.
- 2. Sew center back seam, press the seam apart and serge up to waist. Sew back yoke to yoke, press towards top.
- 3. Sew front yoke to front, press towards top.
- 4. Mark closure slit with three lines, on the right side of right button stand (centre front facing). The first line should be parallel to vertical edge of closure and runs at 1.5 cm from the edge when ready, the second and third line mark the length of closure. Pin lining (should be with fusible interfacing applied!) onto the centre front facing, right sides together, matching the edge of lining with the marked line. Stitch at 0.5 cm from the marked line along the closure slit up to the lines that mark the closure length. Pin the second closure lining, matching its edge with the stitched line, and stitch at 0.5 cm. Check if the stitches are parallel on the wrong side. Cut the slit. Clip into corners at 1.5 cm from the closure ends. Turn the linings onto wrong side through the resulting opening, making a slit frame, which equals the distance between stitch lines. Sew a fixing stitch in the ditch of the lining seam. Press the second lining towards inner edge of centre front facing and sew a fixing stitch at 0.1 cm from the lining seam. Mark and make buttonholes. They are made on centre front facing and interfaced lining. Straighten the ends of closure and fix them from the wrong side, with double stitch at the base of corners. Sew edges of lining. Make short fastening stitches between each pair of buttonholes, the length of the fixing stitch equals the width of the frame. Press center front facing.
- 5. Sew side and shoulder seams. Press the seam apart.
- 6. Sew shoulder edges of center front facings and back neckline facing. Press the seam allowances apart.

7. Pin upper collar to lower collar and sew the corners and the outer edge. Start and stop sewing exactly at the marked line of the seam between collar and garment. Turn the collar right side out, straighten and press.
8. Place center front facing onto front right sides together, pin together and sew along the center front edge. Turn center front facings right side out, straighten seams.
9. Sew lower collar into neckline of coat, and upper collar into the neckline formed by back neckline facing and center front facings. Press seam allowances of collar apart and baste together close to the seam.
10. Sew elbow and front seam on sleeve, press seams apart. Sew sleeves into armholes matching notches, adjusting ease on sleeve cap.
11. Sew seams on lining and sew in sleeves. Serge seam allowances from bottom to waist. Fold inside seam allowance of lower edge of lining two times at 1.5 cm and topstitch.
12. Serge, press and finish with hidden stitches seam allowance for hem of garment. Sew lining to inner edges of the central front facings and to back neckline facing. Start and stop stitching at half width of hem fold on the main garment. Clip into seam allowance on inner edge of central front facing close to seam of lining. Fold inside seam allowance of central front facing along the area between bottom edge and clipped seam allowance and finish with hidden stitches. Serge seam of lining and press towards lining.
13. Sew lining to hem of sleeve. Press seam towards lining. Sew decoration to sleeve.
14. Sew hook to inner side of right front, sew eye to left front.

## TECHNICAL DRAWING:

