

Tunic - Выкройка #4790

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing.

Seam allowances: all seams 1 cm; seam allowance for hem of garment - 2.0 cm; seam allowance along upper edge of pocket - 2.5 cm.

О припусках на швы::

- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.

- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:

Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.



РАСКРОЙ:

Обратите внимание при раскрое:

Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроются со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.

При стачивании деталей, обращайтесь внимание на надсечки, они должны совпадать.

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 1 on fold
3. Lower sleeve - cut 2
4. Cuff - cut 2
5. Back facing - cut 2
6. Front facing - cut 2
7. Pocket - cut 2

Fusible interfacing:

1. Cuff - cut 2
2. Back facing - cut 1
3. Front facing - cut 1

Инструкции:

1. Apply fusible interfacing.
2. Depending on your size, your pattern may or may not feature the front bust darts. Sew these darts now if they are present on your pattern, press bulk towards top.
3. Serge the upper edge of pocket, press onto wrong side and topstitch. Serge sides of pocket and press onto wrong side. Topstitch pockets onto front according to markings.
4. Sew outer back facing to back, press towards top. Sew outer front facing to front, press towards top.
5. Sew shoulder seams, press towards the back and serge. Sew lower sleeve to garment, press towards top and serge.
6. Sew side seams, sewing the sleeve edges at the same time, press towards the back and serge.
7. Sew shoulder seams on inner facings, press the seam apart. Serge the outer edge. Pin facing onto neckline, right sides together, and sew. Clip into curves, turn facing right side out, straighten and press. Topstitch inner facing into the seam of outer facing (stitch-in-the-ditch).
8. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise right side out and sew to sleeve, pinning it to wrong side of the garment. Serge the seam allowances, fold cuff onto right side, press.
9. Serge the lower edge of garment, press onto wrong side and topstitch.

Технический рисунок:

