Dress With Yoke - Выкройка #4857



Recommendations on fabric: natural/mixed knit fabric of small stretchiness in contrasting or similar color.

You will also need: dress zipper, knit fusible interfacing, 2 buttons.

Seam allowances: all seams 1 cm; seam allowance for hem of dress and hem of sleeve – 2.0 cm.

Pattern pieces are drafted as seen from the right side, when cutting, please place them with the text and markings down onto the fabric!

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

О работе с эластичными тканями:
Детали выкройки из трикотажа стачиваются специальным эластичным швом или швом зигзаг. Припуск на подгибку низа может быть настрочен двойной иглой для сохранения эластичности. Детали также можно стачать при помощи оверлока. При стачивании оверлоком, пожалуйста, обрежьте припуски на швы до ширины 0.6 - 0.8 см.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric 1:
1. Upper back - cut 2
2. Lower back - cut 2
3. Upper front – cut 1 on fold
4. Lower front - cut 1 on fold

Main fabric 2:
1. Front yoke left - cut 1
2. Front yoke right - cut 1
3. Collar - cut 2
4. Sleeve - cut 2

Fusible interfacing:
1. Collar - cut 1

Инструкции:

1. Apply fusible interfacing to collar and center front facings (whole cut with fronts).

2. Sew waist darts on upper backs, press the inner part towards center. Sew upper back to lower back, press towards top and serge.

3. Serge the center back edges separately. Sew center back seam from neckline to first marking, and from second marking down to hem, press the seam apart. Sew in zipper.

4. Sew waist darts on upper front, press the inner part towards center. Sew upper front to lower front, press towards top and serge.

5. Serge inner edges of center facings on yoke (whole cut with yokes). Press center front facings onto right side and sew upper corner to the marked line. Clip into seam allowance near the line, turn the center front facings onto wrong side, press. Make buttonholes on right yoke. Pin right yoke onto left yoke and baste together along lower edge.

6. Sew front yoke to upper front, serge and press towards bottom.

7. Sew shoulder and side seams, press towards the back and serge.

8. Pin collars right sides together and sew corners and collar fall. Start and stop sewing exactly at the marked line of the seam between collar and garment. Turn finished collar right side out, straighten corners and press. Sew outer edge of collar into neckline, matching round mark on collar with back center seam, press seam allowances towards the collar. Turn under the raw inner edge of collar and stitch in the ditch.

9. Sew sleeve seam, serge and press. Sew sleeves into armholes, matching notches. Serge and press.

10. Serge seam allowance along hem of dress and hem of sleeve, press onto wrong side and topstitch.

11. Sew on buttons on left yoke according to button holes.

Технический рисунок:

