Jacket With One Button - Sewing Pattern #4991

Recommendations on fabric: natural/mixed suiting fabric.

You will also need: fusible interfacing; shoulder pads; 1 button.

Seam allowances: all seams 1 cm. Seam allowance for hem 1.5 cm.



Note on seam allowances:
- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:
Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.

CUTTING:

Note on cutting:
On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.
When sewing the garment, pay attention to notches, they must match up.

Main fabric:
1. Center back – cut 2
2. Side upper back – cut 2
3. Side lower back – cut 2
4. Side lower front – cut 2
5. Side upper front – cut 2
6. Center front – cut 2
7. Lower collar - cut 1

8. Upper collar – cut 1
9. Center front facing – cut 2
10. Back neck facing – cut 1
11. Sleeve – cut 2

Fusible interfacing:
1. Center front facing – cut 2
2. Back neck facing – cut 1
3. Upper collar - cut 1

INSTRUCTIONS:

1. Apply fusible interfacing. Apply fusing on front along the lapel fold , its width should equal 1 cm (fusible interfacing).

2. Sew upper side back to lower side back. Serge seams and press towards top. Sew side back to center back. Press seam apart, serge. Sew and press apart center back seam, serge.

3. Sew upper side front to lower side front. Serge seams and press towards top.Sew side front to center front. Press seam apart, serge.

4. Sew and press apart shoulder and side edges of jacket, press the seam apart and serge.

5. Pin upper collar to lower collar and sew the corners and the outer edge. Start and stop sewing exactly at the marked line of the seam between collar and garment. Trim away corners, snip into seam allowance near the mark. Turn the collar right side out, straighten and press.

6. Sew and press apart the shoulder edges of the back neckline facing and of the center front facing. Serge the outer edge.

7. Place center front facing onto front right sides together, pin together and sew along the center front edge. Sew upwards up to the notch marking the end of collar seam. Trim away corners. Topstitch seam allowance along center front edge onto center front facing along the closure, and onto front along the part, which is folded away. Place stitch line at 0,2 cm from seam. Turn center front facings right side out, straighten seams.

8. Sew the undercollar into the jacket neckline and the upper collar into the neckline of the back facing and center front facings. Press seam allowances of the collar seam apart and slipstitch them together close to the seam.

9. Sew sleeve seam. Serge and press towards back. Sew sleeves into armholes. Serge and press.

10. Serge lower edges of jacket and of sleeve. Fold inside inside and finish with hidden stitches by hand.

11. Make buttonhole on right front, and on left front sew on a button.

TECHNICAL DRAWING:



