

Sewing Pattern — Skirt 5024

Recommendations on fabric: soft wool or rich silk, silk crepe of 150 cm width

You will also need: 1 zipper; 3 buttons; fusible interfacing
If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams

Attention! First of all, please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches. They must match up with corresponding pieces.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Darts: The fold of the dart is always pressed toward the center of your garment, or down toward the hem.

Fabric:

1. Back panel – cut 2
2. Front panel – cut 2
3. Waistband – cut 1
4. Facing – cut 2

Fusible interfacing: apply the interfacing to wrong side of waistband and facings.

INSTRUCTIONS:

1. Sew front and back darts, press toward center.
2. Serge center back edges separately. Sew side seam between zipper mark and slit mark. Sew in zipper.
3. Press slit seam allowances onto wrong side, and topstitch.
4. Trim front panels with facing, press seam allowances apart, serge facing edge, press facing onto wrong side, Topstitch at 2 cm from edge.
5. Sew side seams, serge and press toward back. Topstitch if desired.
6. Sew the waistband to garment upper edge, right sides together. Press joining seam allowances toward waistband. Fold the waistband along the center, and sew ends. Clip corners and turn the waistband right side out. Turn inner side of waistband seam allowance under, and baste or pin it so that it extends beyond the joining seam by 2 mm. Topstitch the inner edge along joining seam from the right side. Make a buttonhole on left end of waistband, sew the button on the right one.
7. Serge lower edge of garment, turn onto wrong side, and topstitch. Sew decorative buttons underneath waistline button.

TECHNICAL DRAWING:

