

Sewing Pattern — Trousers 6040

Recommendations on fabric: cotton fabric of denim type or corduroy of 150 cm width

You will also need: fusing, zipper; 7 buttons

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Back patch pocket – 2 pieces
2. Front patch pocket – 2 pieces
3. Belt loop – 1 piece
4. Patch pocket – 2 pieces
5. Front part – 2 pieces
6. Button catch – 1 piece
7. Back part – 2 pieces
8. Yoke – 2 pieces
9. Patch pocket flap – 4 pieces
10. Back patch pocket flap – 4 pieces
11. Waistband – 1 piece

Fusing: waistband, button catch, flaps

INSTRUCTIONS:

Apply the fusing to wrong side of waistband, button catch and flaps.

Sew yokes to back parts. Press seam allowances toward the yoke, then topstitch.

Front patch pocket: press the pocket entrance diagonal edge allowance to wrong side, turn the edge under, then stitch along the edge. Press the outer edges of front patch pocket to wrong side, then topstitch it on front part along the marking. Topstitch pockets. Tack pockets and garment waist and side edges.

Sew flap details along outer edges (right sides together), then turn right side out, press and topstitch them. Make buttonholes according to marking.

Back patch pocket: press pocket upper edge allowance under, turn the edge under and stitch along the edge. Press outer edges toward inside, then topstitch on the back parts along marking. Stitch turned upwards back patch pocket flap on the right side. Turn the flap downwards, press it and topstitch along the edge.

Sew side seam. Topstitch garment back parts along seams.

Make pleats on the patch pocket according to the marking, press them and make decorative stitches on 3 mm distance from bending. Press the pocket upper allowance into, turn the edge to wrong side and stitch it along the edge.

Press patch pocket outer edges inside, sew the pocket to garment along the marking: begin with pocket side edges (do not catch the pleat), then sew the lower edge.

Sew turned upward patch pocket flap on the garment right side. Turn the flap down, press and topstitch along the edge.

Sew middle seam (up to the closure) and back parts.

Press one-piece closure facing to wrong side: on the left – along front middle line, on the right – 1 cm before front middle seam. Pin turned sideways zipper on the closure right edge, put on it the button catch (folded wrong side together). Coincide them along edges. Stitch all layers. Make fixing stitch along zipper edges. Pin the slit coinciding front middle lines. Stitch zipper free braid to closure left edge facing (do not catch garment front part fabric). Neaten allowances. Make fixing zig zag along edging lower edges (from the wrong side). Topstitch left front part along the closure marking catching facing.

Sew inside leg seams and neaten allowances.

On the belt loop, press lengthwise edges allowance to wrong side on 1 cm width. Fold the stripe along the center, press, sew long edges, topstitch the stripe along the bending. Cut the stripe into 5 equal parts. Sew belt loops to garment upper edge: at front part – near pockets and side seams, at back part – over the middle seam.

Fold the waistband wrong side out, sew ends. Turn it right side out and press. Coincide the waistband and waist edge and sew. Press open edge under, then stitch it to the garment, continuing the decorative topstitching along the waistband.

Turn belt loops upward, turn them under and topstitch on the waistband.

Press the hem under, press along the edge.

Make a buttonhole into waistband left end. Sew the button on the right one.

TECHNICAL DRAWING:

