

## Sewing Pattern — Pants 7082

Recommendations on fabric: velour.

You will also need: fusing; zipper; 1 button.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: 1 cm for all seams, 1.5 cm for hem, 3 cm for side pocket upper edge.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

Fabric:

1. Waistband - 1 piece
2. Yoke - 2 pieces
3. Back part - 2 pieces
4. Upper front part - 2 pieces
5. Middle front part - 2 pieces
6. Lower front part - 2 pieces
7. Pocket - 2 pieces
8. Belt loop - 1 piece
9. Button catch - 1 piece

Fusing: waistband, button catch, pocket entrance allowance

### **INSTRUCTIONS:**

1. Apply the interfacing to the wrong side of the waistband, button catch and pocket entrance allowance.
2. Serge the patch pocket edges: the longer side edge, pocket entrance edge and the lower edge. Press the serged allowance according to the pattern. Topstitch the pocket entrance allowance at 0.5 cm from the edge.
5. Mark the pocket at the front part and topstitch the side and lower pocket sides at 0.2 cm from the

outer pocket edge, leaving the pocket entrance open.

4. Stitch the yoke to the back part, serge the seam and press it on to the yoke. Put a decorative stitch along the seam at 0.5 cm.

5. Stitch the front parts together. Press the seams towards the middle part and make a decorative stitch along the seams.

6. Serge the front and middle edge and the hem of the trousers. Stitch and serge the side and in-seams. Stitch the front edge and the middle edge up to the zipper notch. Put the second stitch along the crotch close to the front and middle stitches.

7. Press one-piece facings of closure onto the wrong side. Stitch the zipper under closure allowance left edge. Stitch zipper free braid to one-piece right edge. Fold button catch along the center and overstitch short lower edge. Topstitch one-piece closure facing on button catch left edge. Topstitch slit right edge catching the facing.

8. Fold the belt loop along the center wrong side out, neaten the edges and overstitch at 0.5-0.7 cm from the edges. Turn it out to the right side, neaten the seam, placing it at the fold line or moving it 0.1-0.2 cm to the inner side, press.

9. Press the waistband along the center, right side out, and neaten waistband lower inner edge. Serge the inner lower waistband edge. Cut the belt loops according to the indicated size and stitch them according to the notches to the upper garment edge.

10. Stitch the waistband to the upper garment edge. Cut seam allowances at the corners and turn out. Stitch the lower serged waistband edge into the attachment seam and press the waistband.

11. Press the hem onto the wrong side and topstitch.

12. Serge a buttonhole on the right side of the waistband, sew the button on the left side of the waistband.

### **TECHNICAL DRAWING:**

