

Sewing Pattern — Cardigan 4122

Recommendations on fabric: thick knitted fabrics of low stretchiness

You will also need: 3 buttons, silk companion fabric for decoration

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: on hem and sleeve edge – 3 cm; other seams - 1 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Central back part – 2 details
2. Side back part – 2 details
3. Side front part – 2 details
4. Central front part – 2 details
5. Buttonstand – 2 details
6. Back neckline facing – 1 detail
7. Sleeve – 2 details

Companion fabric:

1. Facing – 2 details

INSTRUCTIONS:

1. Sew relieve edges of front part. Serge and press the seam towards center. Sew relieve seams on back part. Serge and press the seam towards center. Sew, serge and press middle seam of back part onto left side. Sew shoulder seams of the jacket. Serge and press towards back part.
2. Sew upper edge decoration. Press the seam apart. Stitch loosely along long edges and gather ruffles. Put decoration onto right side of the jacket right side downwards, coinciding inner edge decoration with marked line. Topstitch decoration. Turn decoration aside, coinciding outer edges of decoration and of jacket. Fix on outer edge on 0.5 cm. Off the edge.

3. Sew shoulder seams of back part neckline facings and buttonstands. Serge and press towards back part. Serge outer edge.
4. Put buttonstand with facing onto right side of front part right side downwards, pin together and overstretch buttonstand, front part neckline, back part neckline and hem of the jacket. Stitch from front part side. Topstitch buttonstand seam allowance onto buttonstand. Stitch 0, 2 cm off the seam. Turn buttonstand onto wrong side, slashing on rounded parts. Fasten buttonstand to shoulder edge with hand stitches.
5. Sew edge of sleeve, press seam allowances and serge. Sew sleeves into armholes according to notches, gathering slightly top of rounding. Press seam allowances and serge.
6. Serge hem of the jacket, turn inside and topstitch.
7. Serge hem of sleeve, turn seam allowance inwards and topstitch.
8. Serge buttonholes on right front part, sew buttons on left one.

TECHNICAL DRAWING:

