

Sewing Pattern — Blouse 4267

Recommendations on fabric: light fabric suitable for dresses/blouses, chiffon

You will also need: companion fabric, 6 buttons, fusing


If the pattern has double contour the seam allowances are included.

If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out and cutting details.

Seam allowances: lower edges of front part, back part and buttonstand — 1.5 cm, outer edge of the flounce — 0 cm, all other seams - 1 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Main fabric:

1. Right front part – 1 detail
2. Left front part – 1 detail
3. Yoke – 1 detail
4. Back part – 1 folded detail
5. Buttonstand — 2 details
6. Placket — 2 details
7. Stand-up part of collar - 1 folded detail

Companion fabric:

1. Flounce — 1 detail

Fusing:

1. Placket — 2 details

ATTENTION! Legend are made on right side of the patterns.

INSTRUCTIONS:

1. Apply fusing to plackets.
2. Sew darts on front part details. Press depths downwards. Make pleats on left front part. Put fixing stitches along inner folds. Make depths of pleats upwards. Fix pleats with temporary stitches along the armhole and neckline edges.

3. Slash seam allowance of the flounce at the notch level. Overstitch seam allowance from the notch up to hem with baby hem. To do that: press seam allowance onto wrong side at 1 cm, stitch up at 0.1-0.2 cm off the fold. Cut off seam allowance close to the stitch. Turn seam allowance inside once again and put the stitch on previous one. Press the seam. Overstitch outer edge of the flounce with rolled seam. Put flounce onto right front part and level edges. Fix with temporary stitch along shoulder edge, neckline and buttonstand. Stitch the placket to left and right front part buttonstands. Turn plackets onto right side. Press the seam onto panel.
4. Stitch loosely along top edge of back part between notches and gather ruffles. Stitch yoke to back part. Serge seam allowance and press it downwards.
5. Sew shoulder seams. Serge seam allowances and press them towards back part.
6. Serge outer edge of buttonstand. Put buttonstand onto the blouse and overstitch buttonstand. Turn buttonstand onto wrong side. Put fixing stitch along buttonstand at 0.2 cm off the edge. Fasten seam allowance of buttonstand shoulder edge to shoulder seam. Level neckline edges.
7. Fold stand-up part of collar in half lengthwise right sides together. Overstitch ends of stand-up part. Cut seam allowances in corners and turn stand-up part of collar onto right side. Sew outer stand-up part of collar into the neckline. Turn inside seam allowance of inner stand-up part of collar and topstitch into outer stand-up part connecting seam.
8. Cut a bias tape from companion fabric as long as the armhole, and of 3.5 cm wide. Fold the bias tape in half lengthwise and press. Put the bias tape onto wrong side of the armhole and stitch. Turn the bias tape onto right side and topstitch. (on right front part make that in two steps). Sew side seams. Serge seam allowances and press them onto back part. Make barred end on side seams at the armhole level.
9. Serge lower edge of the blouse. Turn onto wrong side, press and topstitch.
10. Make buttonholes and sew buttons.

TECHNICAL DRAWING:

