

Sewing Pattern — Dress - costume 5879

Recommendations on fabric: natural / mixed thin costume fabric.

You will also need: fusing; zipper; lining; 5 buttons; clasper

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams -1 cm, lower edge - 3 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



CUTTING:

Fabric:

1. Central back part - 2 details
2. Side back part - 2 details
3. Back part facing - 2 details
4. Side upper front part - 2 details
5. Central upper front part – 2 details
6. Lower front part - 2 details
7. Right strap– 1 detail
8. Left strap – 1 detail
9. Right part of the belt – 1 detail
10. Left part of the belt – 1 detail

Lining:

1. Central upper back part - 2 details
2. Side upper back part - 2 details
3. Side upper front part - 2 details (main fabric patterns are used)
4. Central upper front part – 2 details (main fabric patterns are used)
5. Lower front part – 2 details

Fusing:

1. Back part facing - 1 detail
2. Central upper front part – 2 details
3. Right part of the belt – 1 detail
4. Left part of the belt – 1 detail

INSTRUCTIONS:

1. Apply fusing to corresponding details .
2. Fold straps details in half lengthwise right sides together and overstitch along one long and one short sides, turn onto right side, press.
3. Sew center edge of back part together with the vent up to hem. Press seam allowances and vent onto left side and serge. Topstitch vent seam allowances alongno top edge with machine stitch. Sew princess seams on back part, inserting straps, press seam allowances towards center and serge.
4. Sew princess edges of upper front part, press seam allowances towards center. Sew princess edges of upper front part lining, press seam allowances towards center. Join lining with main fabric right sides together and overstitch along the perimeter, leaving shoulder and side edges open. Slash seam allowances on rounded parts, cut in corners, turn waistcoat onto right side, press.
5. Sew darts on lower front part, press depths towards center. Sew darts on lining of lower front part, press depths towards center. Serge lower edge of lining. Put detail of lining onto main fabric detail wrong sides together, fix along edges and then sew as one detail.
6. Cut off one-piece seam allowance for closure on left lower front part, leaving 2 cm. Serge center edges. Sew center edge from fly piece downwards up to slit marker. Press apart the seam, pressing the slit. Put decorative stitch by 0.1 cm off the edge of the slit.
7. Press one-piece seam allowance for closure that is on right part onto wrong side along front center line, on left part — at 1 cm off the edge. Stitch zipper under left allowance edge, placing zipper blade close by the fold. Pin the panels, aligning center lines. Stitch free tape of the zipper to allowance of closure's right side, without catching front panel fabric. Put decorative stitch on right panel.
8. Press details of the belt in half lengthwise wrong sides together and serge lower inner edges. Stitch belt to top edge of the skirt. Overstitch ends of the belt, slash seam allowances in corners and turn. Topstitch lower serged edge of the belt into connecting seam.
9. Put waistcoat onto the skirt and fix along side edge.
10. Sew details of back part lining the same way as main fabric details. Join lining to main fabric and overstitch edges of armholes, finishing the stitch exactly near side seam marked line. Slash seam allowances on rounded parts.
11. Insert front part between lining and main fabric of back part and sew side edges. Serge seam allowances, press towards back part, turn garment onto right side.
12. Stitch the facing of back part to top edge of back part, press seam onto the facing. Sew shoulder seams (seam allowances of back part neckline and lower edge on facing overhang at 1 cm). Join facing details right sides together and overstitch the neckline. Slash seam allowances, turn the facing onto wrong side, turn free shoulder edge of lower facing inside and fasten. Press lower edge of inner facing inwards and topstitch into connecting seam of outer facing, sewing facings together on free sections.
13. Serge lower edge of the garment, press onto wrong side and undersew with invisible stitches.
14. Serge buttonholes on right front part of the waistcoat and on right belt, sew buttons on left parts.

TECHNICAL DRAWING:

