

## Sewing Pattern — Dress 4257

Recommendations on fabric: natural or mixed fabrics suitable for dresses

You will also need: blind zipper, bias tape, fusing

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: hem of the dress — 2 cm, hem of sleeve — 1.5 cm, outer contour of the rose — 0 cm, all other seams — 1 cm

**Attention!** First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

#### Main fabric:

1. Upper right central part - 1 detail
2. Upper left central part - 1 detail
3. Upper side part of the front - 2 details
4. Upper side part of the back — 2 details
5. Upper central part of the back — 2 details
6. Lower side part of the back — 2 details
7. Lower central part of the back — 2 details
8. Lower front part — 1 detail
9. Sleeve — 2 details
10. Front neckline facing — 2 details
11. Back neckline facing — 2 details
12. Rose — 4 details
13. Right part yoke — 1 detail

#### Fusing:

1. Back neckline facing — 2 details
2. Front neckline facing — 2 details

## **INSTRUCTIONS:**

1. Apply fusing to details. Sew shoulder seams of the facings. Press the seam apart. Serge outer edge of the facings.
2. Sew darts on central part of the back. Press depths towards center. Sew princess seams on the back part on top parts. Serge seam allowances and press them onto central part. Sew princess seams on the back on lower parts. Serge seam allowances and press them onto central part. Sew upper and lower parts of the back. Serge seam allowances and press them downwards. Serge center edge of the back. Sew the edge from hem up to the zipper notches. Sew in zipper.
3. Sew straight edges of the rose. Press apart the seam. Fold roses right sides out and fix with temporary stitch along outer contour. Overstitch outer edge of rose with bias tape. Stitch loosely along inner edge and gather ruffles. Make a «rose» decoration and stitch to right part of the front. Stitch yoke of the front to the front. Serge seam allowance.
4. Sew princess edges of the front. Serge and press the seam towards center.
5. Sew shoulder seams of upper part. Serge seam allowances and press them towards back part. Overstitch the neckline. Turn facings onto wrong side and fix to shoulder seams by hand.
6. Cut the depth of darts in the center, leaving 2-3 cm to the top. Stitch loosely along decorative dart contour on lower front part and gather ruffles. Sew the dart. Cut the depth off with the serger. Put right upper part onto left and fix with temporary stitch along the lower edge. Sew upper and lower front parts. Serge seam allowance and press downwards.
7. Serge hem of sleeve, press onto wrong side and topstitch. Sew sleeve into armhole, leveling notches. Cut seam allowance up to 0.5 cm from the stitch and overstitch the whole armhole along contour with bias tape.
8. Sew side seams. Serge seam allowance and press it towards back part. Make barred ends near side seam at armhole level.
9. Serge hem of the garment, press onto wrong side and topstitch.

## **TECHNICAL DRAWING:**

