

# Sewing Pattern — Skirt 4229

Recommendations on fabric: natural or mixed thin costume fabrics

You will also need: blind zipper, fusing.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm, along center edge of back part - 1. 5 cm, hem of the garment – 3 cm.

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



## **CUTTING**:

## Main fabric:

- 1. Back part 2 details
- 2. Right part of front panel 1 detail
- 3. Left part of front panel 1 detail
- 4. Right fly part 2 details
- 5. Left fly part 2 details
- 6. Flounce 1 detail
- 7. Back part Facing- 2 details
- 8. Front part facing 1 detail
- 9. Strap 1 detail

#### Fusing:

- 1. Back part facing- 2 details
- 2. Front part facing 1 detail

#### **INSTRUCTIONS:**



- 1. Apply fusing to facings of upper edge.
- 2. Sew darts on back panel details, press depths towards center.
- 3. Serge center edges of back part. Sew center edge of back part from zipper marker up to slit marker. Press the seam apart, pressing the slit for zipper and lower slit. Sew zipper in.
- 4. Fold the flounce in half lengthwise right sides together and overstitch the edge from fold up to marker «o». Slash seam allowances away in corners, slash near marker, turn flounce onto right side, straighten, press.
- 5. Make and fasten plaits on front part details. Sew details of left and right front panels, inserting the flounce between them. Press seam allowances to left side edge and serge. Make a pleat on flounce and tack it along upper edge to front panel.
- 6. Sew right part of fly panel to left part, press seam allowances apart. Fold details of fly panel right sides together and overstitch top and lower edges. Slash seam allowances on rounded parts, turn detail onto right side, straighten, press.
- 7. Fold strap in half lengthwise right sides together and sew longitudinal edges. Turn the strap onto right side, press, placing seam in the center of the detail. Serge short edges. Envelope the fly panels connecting seam with the strap and sew the strap into ring. Put fly panel onto front part, leaving 1 cm to top edge, and fix along side edges.
- 8. Sew side seams, press seam onto back part and serge.
- 9. Sew side seams of the facings. Serge lower edge. Fold the facing with the skirt right sides together and overstitch upper edge. Topstitch seam allowances onto the facing by 0, 2 cm off the seam. Turn facings onto wrong side, press. Turn center edges of facing inside and sew to zipper tape.
- 10. Serge lower edge of the skirt, press onto wrong side and undersew with invisible stitches. Topstitch lower slit at 0. 1 cm off the edge.

# **TECHNICAL DRAWING:**



