

Sewing Pattern — Jacket 4223

Recommendations on fabric: thin costume fabric of natural or mixed fibers.

You will also need: fusing; lining; shoulder pads, sleeve heads; 3 buttons.

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams - 1 cm; on hem of sleeve and hem of the garment - 3.5 cm .

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.

ATTENTION: Lining details are cut as main fabric details except for the width of back part neckline facing and buttonstand correspondingly.

CUTTING:

Fabric:

1. Central back part – 2 details
2. Side back part – 2 details
3. Back part inset — 1 detail
4. Lower back part – 1 detail
5. Central front part – 2 details
6. Front part inset – 2 details
7. Lower front part – 2 details
8. Upper sleeve part – 2 details
9. Lower sleeve part – 2 details
10. Back neckline facing – 1 detail
11. Buttonstand – 2 details
12. Decorative buttonstand – 2 details

Lining:

1. Central back part – 2 details
2. Central front part – 2 details
3. Side back part – 2 details
4. Front part inset – 2 details
5. Back part inset — 1 detail
6. Upper sleeve part – 2 details



7. Lower sleeve part – 2 details
8. Lower front part – 2 details
9. Lower back part – 1 detail

Fusing: central front part, back part neckline facing, hem of sleeve, buttonstand, decorative buttonstand

INSTRUCTIONS:

1. Apply fusing to details . Apply fusing to the neckline of back part and hem of sleeve.
2. Sew darts on back part, press depths towards center. Sew relieve edges on back part. Press apart the seam towards center. Sew middle edge of back part. Press seam allowance apart.
3. Sew plaits on front part according to markers. Press depths towards center.
4. Stitch insets to front part and back part. Stitch lower parts. Press apart the seam.
5. Sew and press apart side and shoulder edges of jacket.
6. Fold decorative buttonstand in half lengthwise and overstretch top section. Turn onto right side and press. Stitch decorative buttonstand to jacket stand part.
7. Sew and press apart elbow sleeve seam. Press hem of sleeve. Sew and press apart front sleeve seam. Stitch loosely along rounded part edge and gather ruffles. Sew sleeves into armholes according to notches. Sew in shoulder pads, sew sleeve heads.
8. Sew seams on lining details and sew in sleeves, leaving a slit in front right seam of sleeve. Sew shoulder seams of buttonstands and facing. Press apart the seam. Stitch lining to buttonstands and facing.
9. Lay buttonstand onto right side of front part right side downwards, pin together and overstretch along buttonstand and along neckline. Stitch lower edges of buttonstands to front part exactly on hem turning marked line, leaving 1,5 cm to inner edge of buttonstand. Cut seam allowances in corners. Turn stand parts onto right side, straighten seams. Press lower edge of the garment onto wrong side. Stitch lining to hem of the garment and to hem of sleeve. Turn jacket through the slit. Sew the slit.
10. Serge buttonholes on right front part, sew buttons on left front part.

TECHNICAL DRAWING:

