Dress With Asymmetrical Collar - Выкройка #2083



Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 1 zipper.

Seam allowances: all seams 1 cm; seam allowance for hem of dress – 2.0 cm; seam allowance for hem of sleeve – 1.2 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Upper center back
2. Lower center back – cut 2
3. Back side - cut 2
4. Lower side back - cut 2
5. Front side - cut 2
6. Lower side front – cut 2
7. Right center front – cut 1

8. Left center front – cut 1
9. Lower front – cut 1
10. Center front facing left – cut 1
11. Center front facing right – cut 1
12. Back neck facing – cut 2
13. Sleeve – cut 2

Fusible interfacing:
1. Back neck facing – cut 2
2. Center front facing right – cut 1
3. Center front facing left – cut 1

Инструкции:

1. Apply fusible interfacing.

2. Serge outer edges of center front facings and outer edges of back neckline facings.

3. Pin left center front facing onto left front and sew along neckline edge. Center front facing fold onto wrong side and press. Serge slanted edge. Sew center front facing to Right Front. Trim corner. Turn center front facing onto wrong side and press. Pin right front onto left front and topstitch along the marked line. Fold lapel.

4. Sew front side to front, serge seams and press towards center. Sew lower fronts together. Serge seams and press towards center. Sew upper front to lower front. Serge and press towards top.

5. Sew Side Back to Back, serge seams and press towards center. Sew lower backs together. Serge seams and press towards center. Sew upper backs to lower backs. Serge seams and press towards top.

6. Serge the center back edges separately. Sew the seam from zipper mark down to hem. Press the seam apart, sew in zipper.

7. Pin neckline facing onto Back and sew neckline exactly up to the marked line of shoulder seam. Clip seam allowances, fold facing onto wrong side and press. Slipstitch facing to zipper tape.

8. Sew shoulder seams, inserting Front between Back and Back Facing. Press seams towards back and serge.

9. Sew sleeve seam, serge. Sew sleeves into armholes. Serge the seam allowances.

10. Serge hem of dress and hem of sleeve, press onto wrong side and topstitch.

Технический рисунок:

