Dress With A 2-Tiered Skirt - Выкройка #2124

Recommendations on fabric: natural/mixed fabric suitable for dresses.



You will also need: fusing tape; bias tape of the same colour (approximate length is given on the pattern block for lower back); 17 buttons.

Seam allowances: all seams 1 cm. Seam allowance along hem of garment – 2.0 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Upper back – cut 2
2. Back inset – cut 1
3. Lower back - cut 2
4. Back flounce – cut 1 on fold
5. Front flounce – cut 2
6. Lower front – cut 2

7. Front inset – cut 2
8. Upper front – cut 2
9. Sleeve – cut 2
10. Cuff – cut 2

Инструкции:

1. Apply fusing tape to: the edge of back neckline, the edge of front neckline, center edges of front insets, center edges of lower front, center edges of front flounces.

2. Sew darts on upper backs, press bulk towards center of pieces. Sew center seam of upper back, press towards left and serge. Sew back inset to upper back, press seam allowances towards inset and serge.

3. Sew center seam on lower back, press towards left and serge. Sew a gathering stitch along the upper edge of lower back and gather fullness. Sew lower back to back inset, press towards top and serge.

4. Sew a gathering stitch along the upper edge of back flounce and gather fullness. Sew flounce to lower back, press towards top and serge.

5. Sew a gathering stitch along the lower edge of upper front and gather fullness. Sew front inset to upper front, press seam allowances towards inset and serge.

6. Sew a gathering stitch along upper edge of lower front and gather fullness. Sew lower front to front inset, press towards top and serge.

7. Sew a gathering stitch along the upper edge of the front flounce and gather fullness. Sew flounce to lower front, press towards top and serge.

8. Sew side and shoulder seams, press towards the back and serge.

9. Cut a bias tape, 2.5 cm wide, for button loops. Fold tape in half lengthwise right sides together and stitch at 0.3 cm from fold. Cut away seam allowances close to seam, turn tape right side out and straighten the rolled piece. Cut into parts. Adjust the length of buttonholes. Topstitch button loops onto right front (folds are directed away from the edge).

10. Fold bias tape in half lengthwise right side out and press. Pin bias tape onto center front edge and the edge of neckline from the right side and sew, fold the bias tape onto wrong side and topstitch onto main piece along the fold.

11. Sew sleeve seam, press towards the back and serge. Sew a gathering stitch along a sleeve cap and gather fullness. Sew sleeves into armholes matching notches and adjusting ease, serge and press.

12. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise right side out and press. Sew outer

side of cuff to sleeve, turn under seam allowance of the inner cuff and stitch in the ditch into the seam of the outer cuff.

13. Serge the lower edge of garment, press onto wrong side and topstitch.

14. Sew on buttons on left front.

Tip: you may use a ready button loop tape instead of making the button loops yourself. In this case, skip step 9 and topstitch button loop tape onto the center front edge after completing step 10.

Технический рисунок:

