Dress With A Patch Pocket - Выкройка #2155

Recommendations on fabric: natural/mixed fabric suitable for dresses.



You will also need: 4 buttons.

Seam allowances: all seams 1 cm. Seam allowance along hem of garment – 2.0 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Upper back – cut 2
2. Lower back – cut 2
3. Upper front – cut 2
4. Lower front – cut 1 on fold
5. Front side – cut 2
6. Front placket – cut 4
7. Collar – cut 2

8. Stand collar – cut 2
9. Pocket facing – cut 1
10. Pocket – cut 1

Fusible interfacing:
1. Placket – cut 2
2. Collar – cut 1
3. Stand collar – cut 1
4. Pocket facing – cut 1

Инструкции:

1. Apply fusible interfacing.

2. Sew darts on back. Press bulk towards center. Sew upper back to lower back. Serge seams and press towards top. Sew center back seam. Serge seam and press towards left.

3. Sew dart on front. Trim bulk with serger and press towards the center. Sew front side to front. Serge seam and press towards center.

4. Make a box pleat on the pocket and baste it along the lower edge and the upper edge. Fold pocket facing in half lengthwise wrong sides together, and sew it to the upper edge of the pocket. Serge and press towards bottom. Turn under the side seam allowances and the lower seam allowance of the pocket and press. Topstitch the pocket onto the left front according to markings.

5. Sew upper front to lower front. Serge and press towards top.

6. Sew side and shoulder seams, press towards the back and serge.

7. Pin together plackets pairwise right sides together and sew the center edges of the plackets. Plackets turn right side out and press. Sew plackets to right side of front along longer edge, stop at 1 cm from the bottom. Serge the seam allowances. Snip into seam allowance on front, leaving 1 mm to the stitch line. Sew the right placket over the left placket. Thread the ends of plackets inside and sew, fastening the lower edge.

8. Pin upper collar to lower collar, right sides together. Sew ends of collar and collar fall. Trim seam allowances. Turn the collar right side out, straighten and press. Pin stand collars together, right sides together, put ready collar between them, adjust notches and sew, sewing ends of stand collar at the same time. Start and stop sewing exactly at the marked line of seam between stand collar and garment. Turn finished collar right side out and press.

9. Sew outer stand collar with collar into neckline, fold inside open edge of internal stand collar and stitch in the ditch. Sew a decorative stitch along collar and stand collar at 0.1 cm.

10. Cut (or take ready) bias tape, its width should equal 4 cm and length should equal the length of armhole + 4 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape onto armhole edge from the right side, leaving loose ends, and sew. Fold bias tape onto wrong side, clip into seam allowances and topstitch onto main piece along the fold. Press seam.

11. Serge the lower edge of garment, press onto wrong side and topstitch.

12. Make buttonholes and sew on buttons.

Технический рисунок:

