Dress With Decorative Skirt - Выкройка #2234



Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: dress zipper; fusible interfacing.

Seam allowances: all seams 1 cm. Seam allowance along hem – 1.5 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Upper back – cut 2
2. Lower back – cut 2
3. Upper front - cut 1
4. Lower front right – cut 1
5. Lower front left - cut 1
6. Front neck facing – cut 1
7. Back neck facing – cut 2

Fusible interfacing:
1. Front neck facing – cut 1
2. Back neck facing – cut 2

Инструкции:

1. Apply fusible interfacing to neckline facings.

2. Sew darts on back and front, press the bulk of waist darts towards center, press bulk of bust darts towards top.

3. Sew upper back to lower back, press towards top and serge.

4. Serge center back edges separately. Sew center back seam from notch for zipper to bottom. Press apart center seam, pressing the slit at the same time. Sew in zipper.

5. Sew upper front to lower right front up to the marking, clip into seam allowance near the notch, press towards top and serge. Sew upper front to lower left front, sewing lower right part to lower left part at the same time. Press towards top and serge.

6. Sew side and shoulder seams, press towards the back and serge.

7. Sew the shoulder seams of the neckline facings, press the seam apart, serge the outer edge. Pin facing to dress right sides together and sew the neckline. Clip into curves, turn the facing onto the wrong side and press. Slipstitch facing to shoulder seams and to zipper tape.

8. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of armhole + 5 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to armhole edge from the right side and sew. Clip into seam allowances. Fold bias tape onto wrong side and topstitch onto main piece along the fold. Press seam.

9. Serge the lower edge of garment, press onto wrong side and topstitch.

Технический рисунок:

