Dress With Patch Pockets - Выкройка #2476



Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; dress zipper; 5 buttons.

Seam allowances: all seams 1 cm; seam allowance for hem – 1.5 cm.

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Upper center back - cut 2
2. Upper side back - cut 2
3. Back belt - cut 2
4. Lower back - cut 2
5. Front yoke — cut 1
6. Upper center front — cut 2
7. Upper side front — cut 2

8. Front belt - cut 1
9. Lower front — cut 2
10. Pocket – cut 2
11. Back neck facing – cut 2
12. Front neck facing - cut 1

Fusible interfacing:
1. Back neck facing – cut 2
2. Front neck facing - cut 1

Инструкции:

1. Apply fusible interfacing.

2. Sew side backs to center back, press towards center and serge. Sew back belt to upper part, press seam allowances towards belt and serge. Sew upper back to lower back, press seam allowances towards top and serge.

3. Serge the center back edges separately. Sew the center back seam from zipper mark to hem, press the seam apart, pressing the slit for zipper at the same time. Sew in zipper.

4. Sew front darts on front, press bulk towards top. Sew side fronts to front, press towards center and serge. Sew the center seam of the upper front part, press seam allowances towards left and serge.

5. Sew yoke to front, press towards top and serge. Sew front belt to upper piece, press seam allowances towards belt and serge.

6. Apply fusible interfacing to pocket opening. Cut or use ready-made bias tape, its width should equal 4 cm and its length should equal the length of pocket opening + 5 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to pocket opening from the right side and sew. Clip into seam allowances. Fold bias tape onto wrong side and topstitch onto main piece along the fold. Press seam. Serge the center and the lower edges of pocket, press onto wrong side. Pin pocket onto front skirt according to the markings and topstitch. Baste the upper and the side edges of the pocket to the edges of the skirt.

7. Sew the center edge on lower fronts, press seam allowances towards left and serge. Sew upper front to lower front, press towards top and serge.

8. Sew shoulder and side seams, press towards the back and serge.

9. Sew the shoulder seams of the neckline facings, press the seam apart. Serge the outer edge. Pin facing to garment right sides together and sew the neckline. Clip into curves, turn pieces right side out, straighten, press. Slipstitch facing to garment along the shoulder seam and the zipper tape.

10. Cut or use ready-made bias tape, its width should equal 4 cm and length should equal the length of armhole + 5 cm. Fold bias tape in half lengthwise right side out and press. Pin bias tape to armhole edge from the right side and sew. Clip into seam allowances. Fold bias tape onto wrong side and topstitch onto main piece along the fold. Press seam.

11. Serge the lower edge of garment, press onto wrong side and topstitch.

12. Sew on buttons onto the skirt according to the markings.

Технический рисунок:

