# Blouse With Yoke - Выкройка #4764

Recommendations on fabric: natural/mixed fabrics suitable for blouses.



You will also need: fusible interfacing; 10 buttons.

Seam allowances: Seam allowance for hem of garment – 1.5 cm, other seams – 1 cm.

**О припусках на швы::**
*- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.*
*- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.*

**О требуемой длине ткани:**
*Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.*

## РАСКРОЙ:

**Обратите внимание при раскрое:**
*Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.*
*При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.*

Main fabric:

1. Back - cut 1 on fold

2. Back yoke - cut 1

3. Back neck facing - cut 2

4. Front - cut 2

5. Front yoke - cut 2

6. Front neck facing - cut 4

7. Front placket - cut 2

8. Sleeve – cut 2

9. Cuff – cut 2

10. Pocket — cut 1

Fusible interfacing:

1. Back neck facing - cut 2

2. Front neck facing - cut 4

3. Front placket - cut 2

4. Cuff – cut 2

## Инструкции:

1. Apply fusible interfacing.

2. Sew a gathering stitch along upper edge of back and gather fullness. Sew yoke to back, press seam allowances towards yoke and serge. Sew yoke to front, press seam allowances towards yoke and serge.

3. Fold the upper seam allowance of the pocket to the wrong side by 1 cm and press, then fold it again according to the marked line, press and topstitch. Press side and lower seam allowances of pocket onto wrong side. Pin the pocket onto the left front according to markings and topstitch.

4. Press plackets in half lengthwise right side out. Sew outer edge of placket to front. Press towards placket. Fold inner edge of placket inside and topstitch into seam of.

5. Sew side and shoulder seams, press towards the back and serge.

6. Sew the shoulder seams of the neckline facings, press the seam apart. Pin together outer facing and outer

facing right sides together and sew outer edges. Start and stop sewing exactly at the marked line of seam. Clip into curves. Turn the ready facing right side out and press.

7. Sew outer facing into neckline, turn raw edge of outer facing under and stitch in the ditch.

8. Cut slit on sleeve along the marked line. Cut bias tape from main fabric (or take ready), its width should equal 4 cm and length should equal two lengths of slit +4 cm. Fold bias tape in half lengthwise and press. Press outer seam allowances towards center. Sew bias tape to slit of sleeve (pin bias tape to slit edge from the right side and sew, fold bias tape onto wrong side and topstitch onto garment along fold line).

9. Sew sleeve seam, serge and press. Sew sleeves into armholes, serge and press.

10. Fold cuff in half lengthwise, right sides together and sew short sides. Start stitching exactly at the line which marks the seam between cuff and sleeve. Turn cuff right side out and press. Sew outer side of cuff to lower edge of sleeve. Fold inside inner side of cuff and topstitch into seam of.

11. Serge the lower edge of garment, press onto wrong side and topstitch.

12. Make buttonholes on right front, sew on buttons on the left one. Make buttonholes and sew on buttons onto cuffs.

## Технический рисунок:

