Blouse With Pleat - Выкройка #4919

Recommendations on fabric: natural/mixed fabrics suitable for blouses.



You will also need: fusible interfacing.

Seam allowances: Seam allowance along hem of garment – 1.5 cm. Other seams – 1.0 cm

О припусках на швы::
- Если на выкройке двойной контур, припуски на швы уже включены. Они составляют 1 см, если не указано иначе.
- Если у выкройки одинарный контур, припуски на швы не включены, и должны быть добавлены при раскрое.

О требуемой длине ткани:
Внимание! В инструкциях не указано необходимое количество ткани, так как оно зависит от ширины и рисунка ткани, а также Ваших размерных признаков. Прежде всего, распечатайте лекала и разложите их на ширине, соответствующей ширине ткани, которую Вы хотите использовать (обычно от 90 до 150 см), чтобы определить, сколько ткани Вам потребуется. Не забывайте учитывать парные детали и детали со сгибом.

РАСКРОЙ:

Обратите внимание при раскрое:
Обратите внимание на обозначение долевой нити при раскладке деталей. Некоторые детали кроятся со сгибом. Это указано на лекале. Перенесите все отметки и другие особенности дизайна (вытачки и т.п.) с лекала на ткань.
При стачивании деталей, обращайте внимание на надсечки, они должны совпадать.

Main fabric:
1. Back yoke - cut 1 on fold
2. Back - cut 1 on fold
3. Front – cut 2
4. Center front facing – cut 2
5. Stand collar - cut 2
6. Sleeve - cut 2
7. Cuff - cut 2

Fusible interfacing:
1. Center front facing – cut 2
2. Stand collar - cut 1
3. Cuff – cut 2

Инструкции:

1. Apply fusible interfacing.

2. Make a box pleat on upper edge of back. Sew yoke to back, press towards top and serge. Sew outer stand collar into back neckline, clip seam allowances, press towards stand collar.

3. Sew front darts, press bulk towards top. Make and baste pleats on shoulder edge of front (the bulk is directed towards center).

4. Right front. Pin the center front facing to the front right sides together and sew the outer edge. Clip into curves, turn pieces right side out, press.
Left front. Pin center front facing to front right sides together and sew outer edge from shoulder seam to marking. Clip into seam allowances near marking and on curves, turn pieces right side out, press.

5. Put right front onto left front, matching center lines. Sew left front to right front facing, serge and press, serging the open edge of center front facing up to the right shoulder edge at the same time.

6. Serge lower seam allowance of inner stand collar onto wrong side. Pin inner stand collar to outer stand collar right sides together and sew upper edge exactly up to the marked line of shoulder seam. Clip seam allowances.

7. Sew shoulder edges, placing them between inner and outer stand collars. Press seams towards back, serge. Turn pieces right side out. Topstitch the inner collar in the seam of the outer collar.

8. Sew side seams, press towards the back and serge.

9. Sew sleeve seams, press towards back and serge. Sew sleeves into armholes, serge and press.

10. Sew cuff into a ring, press the seam apart. Fold cuff in half lengthwise, right sides together and press. Sew outer side of cuff to sleeve, fold the seam allowance of the inner cuff inward and stitch in the seam attaching the outer cuff.

11. Serge lower edge of garment, press onto wrong side and topstitch.

12. Fix right and left fronts together at the lower angle of the neckline-with decorative stitch, decorative button, or a brooch.

Технический рисунок:

