

Sewing Pattern — Top 4020

Recommendations on fabric: stretch knit fabric of natural or mixed fibers


If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

SEAM ALLOWANCE: on hem, on back part neckline edge, on top edge of front part, on back part and front part armhole edges, on panel edge of front part from shoulder seam up to marker –1.5 cm, all other seams 0.7 cm

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to take into account pieces to be duplicated or cut on a fold.

When sewing the garment, pay attention to notches, they must match up with corresponding pieces.



CUTTING:

(On the pattern pieces, “beam” means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.)

Advice:

Knit fabric pieces are sewn together with special elastic or narrow zig-zag stitch. Seam allowance on hem is stitched with twin needles to save stretchiness. Pieces can also be sewn together with 3 or 4 – thread serger. When serging, cut seam allowances to 0.6 – 0.8 cm.

Main fabric:

1. Back – cut 1
2. Front – cut 1
3. Side front detail –cut 2

INSTRUCTIONS:

1. Serge neck edge of front, press onto wrong side and topstitch. Make pleats and baste in place according to markers.
2. Sew front to side front details, trim seam allowances near notches, serge and press toward front side details.
3. Sew side and shoulder seams, serge and press seam toward back.
4. Serge bottom edge of garment, armholes edges, back neckline edge and unsewn edge of side front details. Turn onto wrong side, press and topstitch.

TECHNICAL DRAWING:

