

## Sewing Pattern — Pants 7106

Recommendations on fabric: natural/mixed fabric.

You will also need: fusing; 1 zipper; 1 button; elastic braid (waistband's pattern is developed for 3 cm width). NB! Fabric and trimming handles must combine

If the pattern has double contour the seam allowances are included.

Seam allowances are NOT included by default and need to be added when laying out and cutting details if your pattern has single contour.

Seam allowance: all seams – 1 cm, 3 cm for garment hem

Attention! First of all please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need. Don't forget to count pair parts and symmetrical parts.

When sewing the garment, pay attention to notches, they must coincide.



### **CUTTING:**

Fabric:

1. Waistband – 1 piece
2. Yoke – 2 pieces
3. Upper back part – 2 pieces
4. Lower back part – 2 pieces
5. Upper front part – 2 pieces
6. Lower front part – 2 pieces
7. Back pocket – 2 pieces
8. Side sacking – 2 pieces
9. Side front part – 2 pieces
10. Belt loop – 12 pieces
11. Button catch – 1 piece

Fusing: front waistband, button catch, pocket entrance's allowance.

## **INSTRUCTIONS:**

1. Apply the fusing to wrong side out front waistband, button catch, pocket entrance's allowance.
2. Neaten back pocket along the contour. Press upper edge of back patch pocket into wrong side, fold it under and topstitch. Press pocket's lower/side edges into wrong side (according to the pattern). Topstitch the pocket on upper back part according to marks.
3. Stitch side sacking on upper front part. Fold the sacking into wrong side, slash the seam and fix with a stitch at 0.1 cm from the edge.
4. Lay front pocket's side under upper front part, stitch the sacking and neaten the seam. Fix the pocket along upper/side edges.
5. Stitch the yoke to back part. Neaten joining seam and press it towards the yoke. Topstitch at 0.5 cm from joining seam.
6. Stitch upper back parts to lower back parts. Press seams upwards and topstitch along seams.
7. Neaten front/middle edges of trousers as well as hems. Stitch inseams and neaten them, press them backwards. Stitch side seams, press them apart and neaten. Stitch front/middle edges up to closure clit. Make another stitch along crotch seam close to stitch joining front/middle seams.
8. Press closure one-piece facing into wrong side. Stitch the zipper under closure left edge. Stitch zipper free braid to right one-piece facing. Fold button catch along the center and overstitch short lower edge. Topstitch closure one-piece facing on button catch on left edge. Topstitch slit's right edge catching the facing.
9. Fold belt loop wrong side out, overstitch. Turn belt loop right side out, make a stitch of 0.1-0.2 cm width and press it.
10. Press the waistband along the enter right side out and neaten lower inner edge.
11. Stitch the waistband to pants' upper edge. Lay elastic braid on the waistband at back part's level. The braid must overlap side seams by 1 cm. Make fixing stitch at side seams' level (make facultative stitch to fix the zipper at waistband's middle). Overstitch waistband's ends, cut corners' allowances and turn the detail right side out. Topstitch waistband's lower neaten edge along joining seam and press ready waistband. Topstitch belt loops' shaped edges on the seam joining the waistband. Fold upper edge under and topstitch on waistband's upper edge.
12. Press hems into wrong side and topstitch.
13. Make a buttonhole into waistband's right edge, sew a button on left one. Press pants.

**TECHNICAL DRAWING:**

