

Top With Wrap - Sewing Pattern #2420

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; decorative buckle; 1 hidden button.


Seam allowances: Seam allowance for hem of garment - 2 cm; other seams - 1 cm.

Note on seam allowances:

- If the pattern has double contour the seam allowances are included. They are 1 cm unless specified otherwise.
- If the pattern has single contour, the seam allowances are NOT included and need to be added when laying out the pattern.

Note on length of fabric:

Attention! The amount of fabric needed for your pattern is not included. It will depend on the selected pattern size, the width, and design of the fabric you plan to use. First, print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm). Measure how much fabric you will need. Don't forget to account for pieces that need to be cut multiple times and pieces that are cut on the fold.



CUTTING:

Note on cutting:

On the pattern pieces, "beam" means straight of grain. Lay out your pieces accordingly. Some pieces will be cut on the fold. This is noted on the pattern piece. Mark all notches and other design features such as pleats etc. from the pattern onto your fabric.

When sewing the garment, pay attention to notches, they must match up.

Main fabric:

1. Back yoke - cut 1
2. Center back - cut 1 on fold
3. Side back - cut 2
4. Front yoke - cut 2
5. Center front - cut 2
6. Side front - cut 2

7. Back armhole facing - cut 4
8. Front armhole facing - cut 4
9. Stand collar - cut 2
10. Center front facing - cut 2
11. Back neck facing - cut 1

Fusible interfacing:

1. Back armhole facing - cut 2
2. Front armhole facing - cut 2
3. Stand collar - cut 1
4. Center front facing - cut 2
5. Back neck facing - cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side backs to center back, press towards center and serge. Sew yoke to back, press towards top and serge. Sew armhole facing to back, press towards facing.
3. Sew side fronts to front, press towards center and serge. Sew yoke to front, press seam allowances towards yoke and serge. Sew armhole facing to front, press towards facing.
4. Sew side and shoulder seams, press seams towards back and serge.
5. Pin stand collars together, right sides together and sew the ends and the upper edge. Turn stand collar right side out, straighten and press. Sew the stand collar into neckline.
6. Sew side seams of center front facings and back neckline facings, press seam apart. Serge outer edge. Cut away the strap on the left front and the left center front facing. Pin center front facings onto shell right sides together and sew the front neckline and the back neckline (stand collar is placed between the facing and the main part), the shaped edge. Clip into curves, trim away corners, turn pieces right side out, straighten, press.
7. Sew the side edges and the shoulder edges of the inner armhole facings, press seam apart. Serge outer edge. Pin facings onto the garment and sew the armhole edges. Clip into curves, turn pieces right side out, straighten, press. Topstitch inner facings into the seam of outer facings (stitch-in-the-ditch).
8. Serge lower edge of garment, press onto wrong side and topstitch.
9. Sew on the buckle onto the left side seam. Make a hidden button hole on the left front. Sew on hidden button.

TECHNICAL DRAWING:

